



Outlook 2003 Setup

Open Outlook and go to Tools -> Email Accounts.



Select "Add a new e-mail account" and then click Next.



Select POP3 as your server type and click Next.

The screenshot shows the 'E-mail Accounts' dialog box with the 'Server Type' section selected. The title bar reads 'E-mail Accounts'. Below the title bar, the text says 'Server Type' and 'You can choose the type of server your new e-mail account will work with.' There are five radio button options: 'Microsoft Exchange Server', 'POP3', 'IMAP', 'HTTP', and 'Additional Server Types'. The 'POP3' option is selected, indicated by a green dot. At the bottom of the dialog, there are three buttons: '< Back', 'Next >', and 'Cancel'.

Your Name: Enter your name as you want it to appear on outgoing messages.

E-mail Address: Enter your email address.

Incoming mail server: pop.fusemail.net

Outgoing mail server: smtp.fusemail.net


User name: Enter your email username.

Password: Enter your email password.

Leave "Log on using Secure Password Authentication" unchecked and click "More Settings".

The screenshot shows the 'E-mail Accounts' dialog box with the 'Internet E-mail Settings (IMAP)' section selected. The title bar reads 'E-mail Accounts'. Below the title bar, the text says 'Internet E-mail Settings (IMAP)' and 'Each of these settings are required to get your e-mail account working.' The dialog is divided into three sections: 'User Information', 'Server Information', and 'Logon Information'. In 'User Information', 'Your Name' is 'John Smith' and 'E-mail Address' is 'demo@solarisweb.com'. In 'Server Information', 'Incoming mail server (IMAP)' is 'pop.fusemail.net' and 'Outgoing mail server (SMTP)' is 'smtp.fusemail.net'. In 'Logon Information', 'User Name' is 'demo@solarisweb.com', 'Password' is masked with asterisks, and the 'Remember password' checkbox is checked. The 'Log on using Secure Password Authentication (SPA)' checkbox is unchecked. A 'More Settings ...' button is located at the bottom right of the settings area. At the bottom of the dialog, there are three buttons: '< Back', 'Next >', and 'Cancel'.

Click on the Outgoing Server tab and check “My outgoing server (SMTP) requires authentication.”
Click OK.



Click on the Advanced change and change your outgoing (SMTP) port from 25 to 2500.

Outgoing server (SMTP): 2500

Click OK to finish your setup.

Click Next and then Finish to complete setup.

